
Starting app server

1. Search and start Anaconda Prompt



2. Activate environment: in prompt type "conda activate dfo"



3. Go to folder where app files are located. Type "cd your/folder"

```
(dfo) C:\Users\bolju>cd C:\Users\bolju\Desktop\Projects\gecko
```

4. Type "python run.py"


```
(dfo) C:\Users\bolju\Desktop\Projects\gecko>python run.py
```

The result should look like this

```
(dfo2) C:\Users\B.Zhumabayev\Desktop\F0\gecko>python run.py
* Restarting with stat
* Debugger is active!
* Debugger PIN: 315-335-365
(14192) wsgi starting up on http://127.0.0.1:5000
```


Your server is on!

You can now go to http://localhost:5000




Configure setup

- 1. Define folder locations and file paths to existing data
- 2. Configure units and format according to the data available.




Load .las DTS files. Raw, output and normalized DTS data folder is specified in Setup.

Check if folder are correct on the load page



Press the button



Raw DTS folder:

 $C:\Users\B.Zhumabayev\Desktop\FO\gecko\data\all\flow$


Output DTS folder:

 $C:\Users\B.Zhumabayev\Desktop\FO\gecko\data\dts_waterfall\flow$





As a result you will get some statistics about the data



Raw DTS folder:

 $C:\Users\B.Zhumabayev\Desktop\FO\gecko\data\all\flow$

Output DTS folder:

C:\Users\B.Zhumabayev\Desktop\FO\gecko\data\dts_waterfall\flow

Load

Timestamp intervals histogram

Bins, minutes	Frequency
12	521
84.085	1
228.255	1

Timestamp min max

Timestamp min: 2017-11-29T20_42_17

Timestamp max: 2017-12-04T11_05_51

Depths intervals


Depth min, m: 130.099

Depth max, m: 1956.299


Depth interval, m: 0.20000000000001705

Trace depth count: 9132

Build completion using this page




You can add/edit/delete completion elements as required



Once done don't forget to save by clicking on save button.

Step 4


Go to Integrated Plot page to see what the data looks like



Loading




Once loaded will look like this




Step 5

Calculate geothermal trace to then apply it to DTS data

Choose period to average traces. Note that this is simple averaging.




Once it's calculated plot on the right will appear to show the final trace.



In case you are confident in geothermal, save it

After saving, a button will become visible that will allows to calculate normalized DTS, which is simple DTS-geothermal.




Once you click on calculate DTS-geothermal button, it calculated normalized DTS and saves it to the folder you specified in Setup page.


Step 6

Go back to Setup


You can now select between DTS and normalized DTS for integrated plotting




Go to Integrated plot. On the left top corner there is a button to configure plot settings to improve visualization



Configure plot





There are multiple options for Colormaps that can be helpful in testing visualization of certain events taking place

